

ISLEVER

JN0-340

Juniper Networks Certified Internet Associate,
J-series (JNCIA-J)

DEMO

<https://www.islever.com/jn0-340.html>

<https://www.islever.com/juniper.html>

For the most up-to-date exam questions and materials, we recommend visiting our website, where you can access the latest content and resources.

QUESTION NO: 1

On a J-series router, what is the default file used for syslog messages?

- A. messages
- B. system
- C. errors
- D. security

Answer: A

QUESTION NO: 2

What value does RIP use to calculate a metric?

- A. Bandwidth
- B. Cost
- C. Hop count
- D. Delay

Answer: C

QUESTION NO: 3

Which of the following loads a factory default configuration onto your router if you do not have access to the router CLI?

- A. Press the power button for more than 5 seconds
- B. Press the power button for less than 5 seconds
- C. Press the configuration button for less than 5 seconds
- D. Press the configuration button for more than 5 seconds

Answer: D

QUESTION NO: 4

Which CLI command displays all static routes in the routing table?

- A. show route static
- B. show route protocol static
- C. show static all
- D. show static route

Answer: B

QUESTION NO: 5

Which J-series router process is responsible for performing autoinstallation?

- A. rpd
- B. dhcpd
- C. slarpd
- D. autod

Answer: D

QUESTION NO: 6

A stateful firewall on a J-series router is applied to which interface?

- A. Untrusted interface
- B. Loopback interface
- C. WAN interface
- D. Trusted interface

Answer: A

QUESTION NO: 7

Which network utility can test for Layer 3 reachability?

- A. ipconfig
- B. BERT
- C. ping
- D. LMI

Answer: C

QUESTION NO: 8

From the top of the configuration hierarchy, which CLI command displays the local AS number configured on the router?

-
- A. show routing-options
 - B. show bgp autonomous-system
 - C. show bgp protocol
 - D. show protocols bgp

Answer: A

QUESTION NO: 9

Which CLI command can assist you with configuration syntax?

- A. help reference
- B. help cli
- C. help apropos
- D. help topic

Answer: A

QUESTION NO: 10

How do you disable the autoinstallation functionality on a J-series router?

- A. Compress the configuration button for more than 5 seconds
- B. Remove the autoinstallation configuration from the router
- C. Return the router to the factory default configuration
- D. Reboot the router using the removable PCMCIA flash

Answer: B

QUESTION NO: 11

How do you disable the autoinstallation functionality on a J-series router?

- A. Return the router to the factory default configuration
- B. Remove the autoinstallation configuration from the router
- C. Compress the configuration button for more than 5 seconds
- D. Reboot the router using the removable PCMCIA flash

Answer: B